

VCS Module

VMD0002

---

# ESTIMATION OF CARBON STOCKS IN THE DEAD WOOD POOL (CP-D)

Version 1.1

27 November 2023

Sectoral Scope 14

Avoided Deforestation Partners and Climate Focus convened the development of version 1.0 of this module. It was authored by Silvestrum Climate Associates (Igino Emmer and Eveline Trines), Winrock International (Dr. Sandra Brown and Dr. Tim Pearson), Carbon Decisions International (Lucio Pedroni), and TerraCarbon (David Shoch).

Version 1.1 of this module was prepared by Verra with support from Tim Pearson.



# CONTENTS

---

<b>1</b>	<b>SUMMARY DESCRIPTION OF THE MODULE .....</b>	<b>4</b>
<b>2</b>	<b>DEFINITIONS .....</b>	<b>4</b>
<b>3</b>	<b>APPLICABILITY CONDITIONS .....</b>	<b>4</b>
<b>4</b>	<b>PROCEDURES .....</b>	<b>4</b>
4.1	Frequency of measurement for baseline dead wood stocks .....	4
4.2	Estimation of carbon stocks of dead wood .....	4
4.3	Part 1: Standing dead wood .....	5
4.4	Part 2: Lying dead wood .....	8
<b>5</b>	<b>DATA AND PARAMETERS .....</b>	<b>9</b>
5.1	Data and Parameters Available at Validation .....	9
5.2	Data and Parameters Monitored .....	11
	<b>DOCUMENT HISTORY .....</b>	<b>16</b>

# 1 SUMMARY DESCRIPTION OF THE MODULE

This module allows for estimation of carbon stocks in dead wood in the baseline case (for both pre- and post-deforestation stocks) and project case.

## 2 DEFINITIONS

All terms in the following module are used inline with VCS program definitions.

## 3 APPLICABILITY CONDITIONS

This module is applicable to all forest types and age classes.

## 4 PROCEDURES

### 4.1 Frequency of measurement for baseline dead wood stocks

Measurements of initial stocks employed in the baseline must take place within  $\pm 5$  years of the project start date, for simplicity referred to here as stocks at  $t=0$ .

Dead wood stock estimates are valid in the baseline (i.e. treated as constant) for 10 years, after which they must be re-estimated from new field measurements (in both the project area and where applicable in the leakage belt). For each stratum, where the re-measured estimate is within the 90% confidence interval of the  $t=0$  estimate, the  $t=0$  stock estimate takes precedence and is re-employed, and where the re-measured estimate is outside (i.e. greater than or less than) the 90% confidence interval of the  $t=0$  estimate, the new stock estimate takes precedence and is used for the subsequent period.

### 4.2 Estimation of carbon stocks of dead wood

The mean carbon stock in dead wood per unit area at time  $t$  is estimated based on field measurements of fixed area plots or sample points using prisms or relascopes, and line transects, employing representative random or systematic sampling.

Dead wood included in the methodology comprises two components – *standing dead wood that is fully dead* (i.e. absence of green leaves and green cambium) and *lying dead wood*.

Considering the differences in the two components, different sampling and estimation procedures shall be used to calculate stocks in dead wood biomass of the two components.

The methods to be followed in the measurement of the standing dead wood and the lying dead wood biomass are outlined below. Procedures are the same for estimation of baseline ( $C_{BSL,DW,i}$ ) and project stocks ( $C_{ACTUAL,DW,i}$ ).

## 4.3 Part 1: Standing dead wood

### Step 1. Estimation of biomass of standing dead trees

**Step 1.1:** Standing dead trees shall be measured using the same criteria (e.g. minimum DBH) used for measuring live trees. Stumps must be inventoried as if they are very short standing dead trees.

**Step 1.2:** The decomposition class (not to be confused with dead wood density class) of the dead tree shall be recorded and the standing dead wood is categorized under two decomposition classes:

1. Tree with branches and twigs that resembles a live tree (except for leaves);
2. Tree with signs of decomposition (other than loss of leaves) including loss of twigs, branches, or crown.

**Step 1.3:** Biomass is estimated using an allometric equation or Biomass Conversion Expansion Factor (BCEF) calculation for live trees in the decomposition class 1; with no outward signs of decomposition (i.e. twigs remaining) wood density is assumed to be comparable to live tree. Calculations are detailed in the module VMD0001. In decomposition class 2, the estimate of biomass should be limited to the main trunk (bole) of the tree, in which case the biomass is calculated converting volume to biomass using the appropriate dead wood density class. Volume is estimated as either the volume of a cone if the top diameter cannot be measured (and is assumed to be zero), or a cylinder (using Smalian's formula) if the top diameter can be measured directly or by using an instrument such as a relascope or laser inventory instrument or estimated using a taper function. Height/length is determined as either the total height in case of a standing bole or the height at the base of the crown if the crown is persistent.

For decomposition class 2, the biomass of standing dead trees is estimated either as (where top diameter is not measured):

$$B_{SDWl,j,sp,i} = \frac{1}{3} * \pi * \left( \frac{BDia_{SDWl,sp,i}}{200} \right)^2 * H_{SDWl,sp,i} * D_{DWdc} \quad (1)$$

Where:

$B_{SDWl,j,sp,i}$  = Biomass of standing dead tree  $l$  from sample plot/point  $sp$  in stratum  $i$ ; t d.m.

$BDia_{SDWl,sp,i}$  = Basal diameter of standing dead tree  $l$  from sample plot/point  $sp$  in stratum  $i$ ; cm

$H_{SDWl,sp,i}$  = Height of standing dead tree  $l$  from sample plot/point  $sp$  in stratum  $i$ ; m

- $D_{DWdc}$  = Mean wood density of dead wood in the density class (dc) – sound (1), intermediate (2), and rotten (3); t d.m. m<sup>-3</sup>  
 $sp$  = 1, 2, 3, ...  $Pi$  sample plots/points in stratum  $i$   
 $i$  = 1, 2, 3, ...  $M$  strata in the project scenario

Or (where top diameter is measured):

$$B_{SDWL,sp,i} = \frac{BDia_{SDWL,sp,i} + TD_{SDWL,sp,i}}{200} * H_{SDWL,sp,i} * D_{DWdc} \quad (2)$$

Where:

- $B_{SDWL,sp,i}$  = Biomass of standing dead tree  $l$  from sample plot/point  $sp$  in stratum  $i$ ; t d.m.  
 $BDia_{SDWL,sp,i}$  = Basal diameter of standing dead tree  $l$  from sample plot/point  $sp$  in stratum  $i$ ; cm  
 $TD_{SDWL,sp,i}$  = Top diameter of standing dead tree  $l$  from sample plot/point  $sp$  in stratum  $i$ ; cm  
 $H_{SDWL,sp,i}$  = Height of standing dead tree  $l$  from sample plot/point  $sp$  in stratum  $i$ ; m  
 $D_{DWdc}$  = Mean wood density of dead wood in the density class (dc) – sound (1), intermediate (2), and rotten (3); t d.m. m<sup>-3</sup>  
 $sp$  = 1, 2, 3, ...  $Pi$  sample plots/points in stratum  $i$   
 $i$  = 1, 2, 3, ...  $M$  strata in the project scenario

## Step 2: Estimation of biomass stock per unit area in standing dead wood

Two methods are available for sampling: either Fixed Area Plots and Point Sampling with Prisms or Relascopes.

### Step 2, Option 1. Fixed Area Plots

**Step 2.1:** Determine the biomass of each standing dead tree present in the sample plot  $sp$  in stratum  $i$  ( $B_{SDWL,sp,i}$ ).

**Step 2.2:** Calculate total biomass stock in standing dead trees present in the sample plot  $sp$  in stratum  $i$ .

$$B_{SDW,sp,i} = \sum_{l=1}^{N_{sp,i}} B_{SDWL,sp,i} \quad (3)$$

Where:

- $B_{SDWL,sp,i}$  = Biomass of standing dead wood in sample plo  $sp$  in stratum  $i$ ; t d.m.  
 $B_{SDWL,sp,i}$  = Biomass of standing dead tree  $l$  in sample plot  $sp$  in stratum  $i$ ; t d.m.  
 $sp$  = 1, 2, 3, ...  $Pi$  sample plots/points in stratum  $i$   
 $i$  = 1, 2, 3, ...  $M$  strata in the project scenario  
 $N_{sp,i}$  = Number of standing dead trees in sample plot  $sp$  of stratum  $i$   
 $l$  = 1, 2, 3, ...  $N_{i,sp,t}$  standing dead trees in sample plot  $sp$  of stratum  $i$

**Step 2.3:** Calculate the mean biomass stock per unit area in standing dead wood for each stratum:

$$B_{SDWi} = \frac{1}{A_{sp,i}} * \sum_{sp=1}^{P_i} B_{SDWsp,i} \quad (4)$$

Where:

- $B_{SDWi}$  = Mean biomass of standing dead wood in stratum  $i$ ; t d.m. ha<sup>-1</sup>
- $B_{SDWsp,i}$  = Biomass of standing dead wood in sample plot  $sp$  in stratum  $i$ ; t d.m.
- $A_{sp,i}$  = Total area of all sample plots in stratum  $i$ ; ha
- $sp$  = 1, 2, 3, ...  $P_i$  sample plots/points in stratum  $i$
- $i$  = 1, 2, 3, ...  $M$  strata in the project scenario

## Step 2, Option 2. Point Sampling

**Step 2.1:** Determine the biomass of each standing dead tree from sample point  $sp$  in stratum  $i$  ( $B_{SDWL,sp,i}$ ).

**Step 2.2:** Calculate total biomass stock in standing dead trees from sample point  $sp$  in stratum  $i$ .

$$B_{SDWsp,i} = \sum_{l=1}^{N_{j,sp,i}} \frac{B_{SDWL,sp,i}}{(3.1415/10000) * ((DBH(100) * D:RAD)^2)} \quad (5)$$

Where:

- $B_{SDWsp,i}$  = Biomass of standing dead wood per unit area at point  $sp$  in stratum  $i$ ; t d.m. ha<sup>-1</sup>
- $B_{SDWL,sp,i,t}$  = Biomass of standing dead tree  $l$  from sample point  $sp$  in stratum  $i$ ; t d.m.
- $DBH$  = Diameter at breast height of standing dead tree  $l$  at point  $sp$  in stratum  $i$ , cm
- $D:RAD$  = Ratio of DBH to plot radius, specific to prism Basal Area Factor (BAF) employed in point sampling
- $l$  = 1, 2, 3, ...  $N_{j,sp,i}$  sequence number of individual standing dead trees at point  $sp$  in stratum  $i$
- $i$  = 1, 2, 3, ...  $M$  strata in the project scenario

**Step 2.3:** Calculate the mean biomass stock per unit area in standing dead wood for each stratum:

$$B_{SDWi} = \frac{1}{N} * \sum_{sp=1}^{P_i} B_{SDWsp,i} \quad (6)$$

Where:

- $B_{SDWi}$  = Mean biomass of standing dead wood in stratum  $i$ ; t d.m. ha<sup>-1</sup>

$B_{SDWsp,i}$	=	Biomass of standing dead wood at point $sp$ in stratum $i$ ; t d.m. ha <sup>-1</sup>
$N$	=	Number of sample points in stratum $i$ ; dimensionless
$sp$	=	1, 2, 3, ... $P_i$ sample points in stratum $i$
$i$	=	1, 2, 3, ... $M$ strata

## 4.4 Part 2: Lying dead wood

**Step 1:** Lying dead wood must be sampled using the line intersect method (Harmon and Sexton 1996)<sup>1</sup>. Two 50-meter lines (164 ft) are established bisecting each sample plot and the diameters of the lying dead wood ( $\geq 10$  cm diameter [ $\geq 3.9$  inches]) intersecting the lines are measured. The first line is oriented along a random bearing, the second line is oriented perpendicular to the first.

**Step 2:** The dead wood is assigned to one of the three density states (sound, intermediate and rotten) using the ‘machete test’, as recommended by IPCC Good Practice Guidance for LULUCF (2003), Section 4.3.3.5.3. Dead wood density class ( $dc$ ) is assessed at the point of intersection with the sample line, as per measured parameters section below.

**Step 3:** The volume of lying dead wood per unit area is estimated using the equation (Warren and Olsen 1964)<sup>2</sup> as modified by Van Wagner (1968)<sup>3</sup> separately for each density state:

$$V_{LDWi} = \frac{1 * \left( \sum_{n=1}^N Dia_{dc,n,i}^2 \right)}{8 * L} \quad (7)$$

Where:

$V_{LDWi}$	=	Volume of lying dead wood per unit area in density class $dc$ in stratum $i$ ; m <sup>3</sup> ha <sup>-1</sup>
$Dia_{n,i,t}$	=	Diameter of piece $n$ of dead wood along the transect in stratum $i$ ; cm
$n$	=	1, 2, 3, ... $N$ sequence number of wood pieces in density class $dc$ intersecting the transect
$L$	=	Length of the transect; 100 m
$dc$	=	Dead wood density class – sound (1), intermediate (2), and rotten (3); dimensionless
$i$	=	1, 2, 3, ... $M$ strata in the project scenario

**Step 4:** Volume of lying dead wood shall be converted into biomass using the following relationship. Density of each dead wood density class ( $D_{DWdc}$ ) is estimated as per guidance in measured parameters section below.

<sup>1</sup> Harmon, M.E. and J. Sexton. (1996) Guidelines for measurements of wood detritus in forest ecosystems. US LTER Publication No. 20. US LTER Network Office, University of Washington, Seattle, WA, USA.

<sup>2</sup> Warren, W.G. and Olsen, P.F. (1964) A line intersect technique for assessing logging waste. *Forest Science* 10: 267-276.

<sup>3</sup> Van Wagner, C.E. (1968). The line intersect method in forest fuel sampling. *Forest Science* 14: 20-26.



$$B_{LDWi} = \sum_{dc=1}^3 V_{LDWdc,i} * D_{DWdc} \quad (8)$$

Where:

- $B_{LDWi}$  = Biomass of lying dead wood per unit area in stratum  $i$ ; d.m. ha<sup>-1</sup>
- $V_{LDWdc,i}$  = Volume of lying dead wood per unit area in density class  $dc$  in stratum  $i$ ; m<sup>3</sup> ha<sup>-1</sup>
- $D_{DWdc}$  = Mean wood density of dead wood in the density class ( $dc$ ) – sound (1), intermediate (2), and rotten (3); t d.m. m<sup>-3</sup>
- $dc$  = Dead wood density class – sound (1), intermediate (2), and rotten (3); dimensionless
- $i$  = 1, 2, 3, ... $M$  strata

**Step 5:** Mean carbon stock in dead wood for each stratum is then calculated as the sum of standing and lying dead wood components, converted to carbon dioxide equivalents.

$$C_{DWi} = ((B_{SDWi} + B_{LDWi}) * CF_{DW}) * \frac{44}{12} \quad (9)$$

Where:

- $C_{DWi}$  = Mean carbon stock of dead wood in stratum  $i$ ; t CO<sub>2</sub>-e ha<sup>-1</sup>
- $B_{SDWi}$  = Biomass of standing dead wood in stratum  $i$ ; t d.m. ha<sup>-1</sup>
- $B_{LDWi}$  = Biomass of lying dead wood in stratum  $i$ ; t d.m. ha<sup>-1</sup>
- $CF_{DW}$  = Carbon fraction of dry matter in dead wood; t C t<sup>-1</sup> d.m.
- $i$  = 1, 2, 3, ... $M$  strata
- $\frac{44}{12}$  = Ratio of molecular weight of CO<sub>2</sub> to carbon, t CO<sub>2</sub>-e t C<sup>-1</sup>

## 5 DATA AND PARAMETERS

### 5.1 Data and Parameters Available at Validation

Data / Parameter	$CF$
Data unit	t C t <sup>-1</sup> d.m.
Description	Carbon fraction of dry matter in t C t <sup>-1</sup> d.m.
Equations	9
Source of data	Default value 0.47 t C t <sup>-1</sup> d.m. per IPCC 2006GL Species-specific values are not required due to difficulty of species determination of dead wood.
Value applied	0.47 t C t <sup>-1</sup> d.m.

Justification of choice of data or description of measurement methods and procedures applied	-
Purpose of Data	Calculation of baseline and project emissions
Comments	-

Data / Parameter	$D:RAD$																		
Data unit	Dimensionless																		
Description	Ratio of DBH to plot radius, specific to prism Basal Area Factor (BAF) employed in point sampling.																		
Equations	5																		
Source of data	-																		
Value applied	<table border="1"> <thead> <tr> <th>BAF (m<sup>2</sup>/ha)</th><th>D:RAD</th></tr> </thead> <tbody> <tr><td>2</td><td>35.4</td></tr> <tr><td>3</td><td>28.9</td></tr> <tr><td>4</td><td>25.0</td></tr> <tr><td>5</td><td>22.4</td></tr> <tr><td>6</td><td>20.4</td></tr> <tr><td>7</td><td>18.9</td></tr> <tr><td>8</td><td>17.7</td></tr> <tr><td>9</td><td>16.7</td></tr> </tbody> </table>	BAF (m <sup>2</sup> /ha)	D:RAD	2	35.4	3	28.9	4	25.0	5	22.4	6	20.4	7	18.9	8	17.7	9	16.7
BAF (m <sup>2</sup> /ha)	D:RAD																		
2	35.4																		
3	28.9																		
4	25.0																		
5	22.4																		
6	20.4																		
7	18.9																		
8	17.7																		
9	16.7																		
Justification of choice of data or description of measurement methods and procedures applied	-																		
Purpose of Data	Calculation of baseline and project emissions																		
Comments	-																		

Data / Parameter	$D_{DWdc}$
Data unit	t d.m. m <sup>-3</sup>
Description	Mean wood density of dead wood in the density class (dc) – sound (1), intermediate (2), and rotten (3); t d.m. m <sup>-3</sup>
Equations	1, 2

Source of data	<p>The source of data shall be chosen with priority from higher to lower preference as follows:</p> <ol style="list-style-type: none"> <li>Research publications relevant to the project area;</li> <li>National species-specific or group of species-specific (e.g. from National GHG inventory);</li> <li>Species-specific or group of species-specific from neighboring countries with similar conditions. Sometimes (c) may be preferable to (b);</li> <li>Global species-specific or group of species-specific (e.g. IPCC GPG-LULUCF).</li> </ol> <p>Species-specific dead wood densities may not always be available, and may be difficult to apply with certainty to decomposed wood and in the typically species rich forests of the humid tropics, hence it is acceptable practice to use dead wood densities developed for forest types.</p>
Value applied	-
Justification of choice of data or description of measurement methods and procedures applied	<p>Project-specific determination of density is most likely necessary, requiring collection of representative samples (in terms of scale and representation of forest strata/species composition similar to the inventory), from a minimum of 20-30 trees from each density class. Density classes need not be determined for specific species or species groups.</p> <p>Dead wood samples are cut in discs and thickness and diameter measured to calculate green volume. Samples are oven dried (70o C) to a constant weight in the laboratory, and density calculated as dry weight (g) per unit green volume (cm<sup>3</sup>), from which mean value and 90% confidence interval are calculated for each density class. For each density class, either:</p> <ul style="list-style-type: none"> <li>If the 90% confidence interval is equal to or less than 10% of the mean, the mean density value is applied in project calculations.</li> <li>If the 90% confidence interval is greater than 10% of the mean, the lower 90% confidence bound of the mean density estimate is applied in project calculations.</li> </ul>
Purpose of Data	Calculation of baseline and project emissions
Comments	-

## 5.2 Data and Parameters Monitored

Data / Parameter:	$Dia_{n,i,t}$
Data unit:	cm
Description:	Diameter of piece $n$ of dead wood along the transect in stratum $i$ , at time $t$ in cm
Equations	7

<b>Source of data:</b>	Field measurements in sample transects
<b>Description of measurement methods and procedures to be applied:</b>	Lying dead wood must be sampled using the line intersect method (Harmon and Sexton 1996 <sup>4</sup> ). Two 50-meter lines are established bisecting each sample plot and the diameters of the lying dead wood ( $\geq 10$ cm diameter) intersecting the lines are measured. The first line is oriented along a random bearing, the second line is oriented perpendicular to the first.
<b>Frequency of monitoring/recording:</b>	Where dead wood is an included pool monitoring must occur at least every ten years for baseline renewal. Where carbon stock enhancement is included and dead wood is an included pool monitoring shall occur at least every five years
<b>QA/QC procedures to be applied:</b>	Standard quality control / quality assurance (QA/QC) procedures for forest inventory including field data collection and data management shall be applied. Use or adaptation of QA/QCs already applied in national forest monitoring, or available from published handbooks, or form the <i>IPCC GPG LULUCF 2003</i> , is recommended.
<b>Purpose of data:</b>	Calculation of baseline and project emissions
<b>Calculation method:</b>	
<b>Comments:</b>	Where carbon stock estimation occurs only for determination of the baseline this parameter shall be known ex-ante. Where part of project monitoring, ex-ante it shall be assumed that dead wood diameters remain constant during the baseline period.

<b>Data / Parameter:</b>	<i>DBH</i>
<b>Data unit:</b>	cm
<b>Description:</b>	Diameter at breast height of standing dead tree in cm
<b>Equations</b>	5
<b>Source of data:</b>	Field measurements from sample plots or points
<b>Description of measurement methods and procedures to be applied:</b>	Typically measured 1.3m aboveground. Measure all standing dead trees above some minimum DBH in the sample plots. Minimum DBH employed in inventories is held constant for the duration of the project.
<b>Frequency of monitoring/recording:</b>	Where dead wood is an included pool monitoring must occur at least every ten years for baseline renewal. Where carbon stock enhancement is included and dead wood is an included pool monitoring shall occur at least every five years
<b>QA/QC procedures to be applied:</b>	Standard quality control / quality assurance (QA/QC) procedures for forest inventory including field data collection and data management shall be applied. Use or adaptation of QA/QCs already applied in national forest monitoring, or available from published handbooks, or form the <i>IPCC GPG LULUCF 2003</i> , is recommended.
<b>Purpose of data:</b>	Calculation of baseline and project emissions

<sup>4</sup> Harmon, M.E. and J. Sexton. (1996) Guidelines for measurements of woody detritus in forest ecosystems. US LTER Publication No. 20. US LTER Network Office, University of Washington, Seattle, WA, USA.

Calculation method:	-
Comments:	Where carbon stock estimation occurs only for determination of the baseline this parameter shall be known ex-ante. Where part of project monitoring, ex-ante it shall be assumed that standing dead wood DBH remains constant during the baseline period.

Data / Parameter:	$BD_{dia}$
Data unit:	cm
Description:	Basal diameter of standing dead tree in cm
Equations	1,2
Source of data:	Field measurements from sample plots/points
Description of measurement methods and procedures to be applied:	Measured at ground level.
Frequency of monitoring/recording:	Where dead wood is an included pool monitoring must occur at least every ten years for baseline renewal. Where carbon stock enhancement is included and dead wood is an included pool monitoring shall occur at least every five years
QA/QC procedures to be applied:	Standard quality control / quality assurance (QA/QC) procedures for forest inventory including field data collection and data management shall be applied. Use or adaptation of QA/QCs already applied in national forest monitoring, or available from published handbooks, or from the IPCC GPG LULUCF 2003, is recommended.
Purpose of data:	Calculation of baseline and project emissions
Calculation method:	-
Comments:	Where carbon stock estimation occurs only for determination of the baseline this parameter shall be known ex-ante. Where part of project monitoring, ex-ante it shall be assumed that basal diameters of standing dead trees remain constant during the baseline period.

Data / Parameter:	$TD_{SDW}$
Data unit:	cm
Description:	Top diameter of standing dead tree in cm
Equations	1,2
Source of data:	Field measurements from sample plots/points
Description of measurement methods and procedures to be applied:	Measured at the top of a standing bole, or if crown persistent at the base of the crown. Measured either directly or by using an instrument such as a relascope or laser inventory instrument.  Top diameter can also be estimated from measured basal diameter and height using a taper function that models diminution of diameter over the height of a tree. Taper functions should be based on empirical data

	relevant to the project area, but need not be species or species-group specific.
<b>Frequency of monitoring/recording:</b>	Where dead wood is an included pool monitoring must occur at least every ten years for baseline renewal. Where carbon stock enhancement is included and dead wood is an included pool monitoring shall occur at least every five years
<b>QA/QC procedures to be applied:</b>	Standard quality control / quality assurance (QA/QC) procedures for forest inventory including field data collection and data management shall be applied. Use or adaptation of QA/QCs already applied in national forest monitoring, or available from published handbooks, or form the <i>IPCC GPG LULUCF 2003</i> , is recommended.
<b>Purpose of data:</b>	Calculation of baseline and project emissions
<b>Calculation method:</b>	-
<b>Comments:</b>	Where carbon stock estimation occurs only for determination of the baseline this parameter shall be known ex-ante. Where part of project monitoring, ex-ante it shall be assumed that basal diameters of standing dead trees remain constant during the baseline period.

<b>Data / Parameter:</b>	$H_{SDW}$
<b>Data unit:</b>	m
<b>Description:</b>	Height of standing dead tree in m
<b>Equations</b>	1,2
<b>Source of data:</b>	Field measurements from sample plots/points
<b>Description of measurement methods and procedures to be applied:</b>	Height measured from ground level to either the top of a standing bole or to the base of crown if crown is persistent. Height is measured either directly or by using an instrument such as a clinometers, relascope or laser inventory instrument.
<b>Frequency of monitoring/recording:</b>	Where dead wood is an included pool monitoring must occur at least every ten years for baseline renewal. Where carbon stock enhancement is included and dead wood is an included pool monitoring shall occur at least every five years
<b>QA/QC procedures to be applied:</b>	Standard quality control / quality assurance (QA/QC) procedures for forest inventory including field data collection and data management shall be applied. Use or adaptation of QA/QCs already applied in national forest monitoring, or available from published handbooks, or form the <i>IPCC GPG LULUCF 2003</i> , is recommended.
<b>Purpose of data:</b>	Calculation of baseline and project emissions
<b>Calculation method:</b>	-
<b>Comments:</b>	Where carbon stock estimation occurs only for determination of the baseline this parameter shall be known ex-ante. Where part of project monitoring, ex-ante it shall be assumed that basal diameters of standing dead trees remain constant during the baseline period.

<b>Data / Parameter:</b>	$Asp$
--------------------------	-------

<b>Data unit:</b>	ha
<b>Description:</b>	Total area of all sample plots in ha
<b>Equations</b>	4
<b>Source of data:</b>	Recording and archiving of number and size of sample plots
<b>Description of measurement methods and procedures to be applied:</b>	-
<b>Frequency of monitoring/recording:</b>	Where dead wood is an included pool monitoring must occur at least every ten years for baseline renewal. Where carbon stock enhancement is included and dead wood is an included pool monitoring shall occur at least every five years
<b>QA/QC procedures to be applied:</b>	-
<b>Purpose of data:</b>	Calculation of baseline and project emissions
<b>Calculation method:</b>	-
<b>Comments:</b>	Where carbon stock estimation occurs only for determination of the baseline this parameter shall be known ex-ante. Where part of project monitoring, ex-ante it shall be assumed that basal diameters of standing dead trees remain constant during the baseline period.

<b>Data / Parameter:</b>	<i>N</i>
<b>Data unit:</b>	Dimensionless
<b>Description:</b>	Number of sample points
<b>Equations</b>	6
<b>Source of data:</b>	Recording and archiving of number of sample points
<b>Description of measurement methods and procedures to be applied:</b>	-
<b>Frequency of monitoring/recording:</b>	Where dead wood is an included pool monitoring must occur at least every ten years for baseline renewal. Where carbon stock enhancement is included and dead wood is an included pool monitoring shall occur at least every five years
<b>QA/QC procedures to be applied:</b>	-
<b>Purpose of data:</b>	Calculation of baseline and project emissions
<b>Calculation method:</b>	-
<b>Comments:</b>	Where carbon stock estimation occurs only for determination of the baseline this parameter shall be known ex-ante. Where part of project monitoring, ex-ante it shall be assumed that basal diameters of standing dead trees remain constant during the baseline period.

# DOCUMENT HISTORY

Version	Date	Comment
v1.0	03 Dec 2010	Initial version
v1.1	23 Nov 2023	<ul style="list-style-type: none"><li>• Update to latest VCS methodology template</li><li>• Removal of references to VM0007</li></ul>