VCS Module

VMD0005

ESTIMATION OF CARBON STOCKS IN THE LONG-TERM WOOD POOL (CP-W)

Version 1.2

27 November 2023

Sectoral Scope 14

Avoided Deforestation Partners and Climate Focus convened the development of version 1.0 of this module. It was authored by Silvestrum Climate Associates (Igino Emmer and Eveline Trines), Winrock International (Dr. Sandra Brown and Dr. Tim Pearson), Carbon Decisions International (Lucio Pedroni), and TerraCarbon (David Shoch).

Version 1.1 of this module was developed by Winrock International and TerraCarbon.

Version 1.2 of this module was developed by Verra with support from Tim Pearson.

CONTENTS

1   SUMMARY DESCRIPTION OF THE MODULE

This module allows for *ex ante* estimation of carbon stocks in the long-term wood products pool in the baseline case. Carbon stocks treated here are those stocks entering the wood products pool at the time of deforestation.

2   DEFINITIONS

All terms in the following module are used inline with VCS program definitions.

3   APPLICABILITY CONDITIONS

This module is applicable to all cases where wood is harvested for conversion to wood products for commercial markets, for all forest types and age classes.

4   PROCEDURES

4.1   Frequency of update of oxidation factors

The approach outlined in this module employs an emission factor (WW) derived by Winjum *et al.* 1998. In the event that new research findings updating or refining (e.g. for specific countries) the WW factor become available in the future (during the project crediting period), they will replace the factors included in the module, otherwise the factors in the module will remain valid. The use of this module requires that project proponents review research findings (that produce emissions factors compatible with the conceptual framework here) at least every 10 years to identify further refinements to the emission factors that are empirically-based and peer-reviewed.

4.2   *Ex ante* estimation of carbon stocks in the wood products pool in the baseline

This module estimates carbon stocks in wood products resulting from timber harvest occurring prior to or in the process of deforestation. Accounting for such wood products must only take place at the time of deforestation.

All factors are derived from Winjum *et al*. 1998.

If approved timber harvest plans, specifying harvest intensity per strata in terms of volume extracted per ha, are available for the project area use Option 1. If approved harvest plans are not available use Option 2.

4.2.1 Option 1: Direct Volume Extraction Estimation

Step 1: Identify the wood product class(es) (ty; defined here as sawnwood, wood-based panels, other industrial roundwood, paper and paper board, and other) that are the anticipated end use of the extracted carbon calculated in Step 2.

Step 2: Calculate the biomass carbon of the volume extracted by wood product type ty from within the project boundary:

$$C_{XB,ty,i} = \frac{1}{A_i} * \sum_{j=1}^{S} \left(V_{ex,ty,j,i} * D_j * CF_j * \frac{44}{12} \right) \tag{1}$$

Where:

$C_{XB,ty,i}$ = Mean stock of extracted biomass carbon by class of wood product ty from stratum i; t CO_2-e ha^{-1}

A_i = Total area of stratum i; ha

$V_{ex,ty,j}$ = Volume of timber extracted from within stratum i (does not include slash left onsite) by species j and wood product class ty; m^3

D_j = Mean wood density of species j; t d.m.m^{-3}

CF_j = Carbon fraction of biomass for tree species j; t C t^{-1} d.m.

j = $1, 2, 3, ...S$ tree species

ty = Wood product class – defined here as sawnwood (s), wood-based panels (w), other industrial roundwood (oir), paper and paper board (p), and other (o)

$\frac{44}{12}$ = Ratio of molecular weight of CO_2 to carbon, t CO_2-e t C^{-1}

Step 3: Calculate the biomass carbon extracted that enters the wood products pool at the time of deforestation.

$$C_{WP,i} = \sum_{ty=s,w,oir,p,o} C_{XB,ty,i} * \left(1 - WW_{ty} \right) \tag{2}$$

Where:

$C_{WP,i}$ = Carbon stock entering the wood products pool from stratum i; t CO_2-e ha^{-1}

$C_{XB,ty,i}$ = Mean stock of extracted biomass carbon by class of wood product ty from stratum i; t CO_2-e ha^{-1}

WW_{ty} = Wood waste. The fraction immediately emitted through mill inefficiency by class of wood product ty; dimensionless

ty = Wood product class – defined here as sawnwood (s), wood-based panels (w), other industrial roundwood (oir), paper and paper board (p), and other (o)

i = $1, 2, 3, ...M$ strata in the project scenario

Step 4: Calculate the amount of wood products entering the pool at the time of deforestation ($C_{WP,i}$, calculated in C_{WP}) that is expected to be emitted over a 100-year timeframe.

$$C_{WP100,i} = C_{WP,i} - C_{WP,i} * (1 - SLFp) * (1 - Ofp) \tag{3}$$

Where:

$C_{WP100,i}$	=	Carbon stock entering the wood products pool at the time of deforestation that is expected to be emitted over 100-years from stratum *i*; t CO₂-e ha⁻¹
$C_{WP,i}$	=	Carbon stock entering wood products pool at time of deforestation from stratum *i*; t CO₂-e ha⁻¹
SLF_{ty}	=	Fraction of wood products that will be emitted to the atmosphere within 5 years of timber harvest by class of wood product *ty*; dimensionless
OF_{ty}	=	Fraction of wood products that will be emitted to the atmosphere between 5 and 100 years of timber harvest by class of wood product *ty*; dimensionless
ty	=	Wood product class – defined here as sawnwood (s), wood-based panels (w), other industrial roundwood (oir), paper and paper board (p), and other (o)
i	=	*1, 2, 3, …M* strata in the project scenario

4.2.2 Option 2: Commercial inventory estimation

Step 1: Calculate the biomass carbon of the commercial volume extracted prior to or in the process of deforestation:

$$C_{XB,i} = C_{AB,tree,i} * \frac{1}{BCEF} * Pcom_i \tag{4}$$

Where:

$C_{XB,i}$	=	Mean stock of extracted biomass carbon from stratum *i*; t CO₂-e ha⁻¹
$C_{AB,tree,i}$	=	Mean aboveground biomass carbon stock in stratum *i*; t CO₂-e ha⁻¹
$BCEF$	=	Biomass conversion and expansion factor (BCEF) for conversion of merchantable volume to total aboveground tree biomass; dimensionless
$Pcom_i$	=	Commercial volume as a percent of total aboveground volume in stratum *i*; dimensionless
i	=	*1, 2, 3, …M* strata in the project scenario

Step 2: Identify the wood product class(es) (ty; defined here as sawnwood, wood-based panels, other industrial roundwood, paper and paper board, and other) that are the anticipated end use of the extracted carbon calculated in Step 1.

Step 3: Calculate the biomass carbon entering the wood products pool at the time of deforestation.

$$C_{WP,i} = \sum_{ty=s,w,oir,p,o} C_{XB,ty,i} * \left(1 - WW_{ty}\right) \tag{5}$$

Where:

$C_{WP,i}$ =   Carbon stock entering the wood products pool from stratum *i*; t CO₂-e ha⁻¹

$C_{XB,ty,i}$ =   Mean stock of extracted biomass carbon by class of wood product *ty* from stratum *i*; t CO₂-e ha⁻¹

WW_{ty} =   Wood waste. The fraction immediately emitted through mill inefficiency by class of wood product *ty*; dimensionless

ty   =   Wood product class – defined here as sawnwood (s), wood-based panels (w), other industrial roundwood (oir), paper and paper board (p), and other (o)

i   =   *1, 2, 3, …M* strata in the project scenario

Step 4: Calculate the amount of wood products entering the pool at the time of deforestation ($C_{WP,i}$, calculated in C_{WP}) that is expected to be emitted over a 100-year timeframe.

$$C_{WP100,i} = C_{WP,i} - C_{WP,i} * (1 - SLFp) * (1 - Ofp) \tag{6}$$

Where:

$C_{WP100,i}$ =   Carbon stock entering the wood products pool at the time of deforestation that is expected to be emitted over 100-years from stratum *i*; t CO₂-e ha⁻¹

$C_{WP,i}$ =   Carbon stock entering wood products pool at time of deforestation from stratum *i*; t CO₂-e ha⁻¹

SLF_{ty} =   Fraction of wood products that will be emitted to the atmosphere within 5 years of timber harvest by class of wood product *ty*; dimensionless

OF_{ty} =   Fraction of wood products that will be emitted to the atmosphere between 5 and 100 years of timber harvest by class of wood product *ty*; dimensionless

ty   =   Wood product class – defined here as sawnwood (s), wood-based panels (w), other industrial roundwood (oir), paper and paper board (p), and other (o)

i   =   *1, 2, 3, …M* strata in the project scenario

6   DATA AND PARAMETERS

6.1   Data and Parameters Available at Validation

Data / Parameter	$BCEF$
Data unit	Dimensionless
Description	Biomass conversion and expansion factor for conversion of commercial wood volume per unit area to total aboveground tree biomass per unit area; note that BCEF as defined here, and in most applications, is not applied on a per stem basis
Equations	1

Source of data	Equations have been derived using a wide range of measured variables (commercial wood volume per unit area and total aboveground biomass per unit area) based on datasets that comprise at least 30 trees. Equations must be based on statistically significant regressions and have an r2 that is ≥ 0.8.
	The source of data shall be chosen with priority from higher to lower preference as follows:
	a) Existing local forest type-specific;
	b) National forest type-specific or eco-region-specific (e.g. from national GHG inventory);
	c) Forest type-specific or eco-region-specific from neighboring countries with similar conditions. Sometimes (c) might be preferable to (b);
	d) Global forest type or eco-region-specific (e.g. IPCC 2006 INV GLs AFOLU Chapter 4 Table 4.5)
	The project volume data to which the selected BCEF is applied must conform to the data the BCEF was originally derived from, in particular, it must match forest type, stand structure, minimum DBH, and cover the range of potential independent variable values (commercial volumes) likely to be encountered in the project area.
	Care must be taken to ensure that the selected BCEF does not account for non-commercial species not represented in commercial volume estimates (i.e. is restricted to expanding merchantable volumes to account for only non-merchantable tree components).
Value applied	-
Justification of choice of data or description of measurement methods and procedures applied	-
Purpose of Data	Calculation of baseline emissions
Comments	Alternatively, BCEF, where not directly available, can be calculated as wood density (t dry mass m-3 green volume) * BEF (Biomass Expansion Factor = ratio of aboveground biomass to biomass of the commercial volume).
	If using BCEFs developed outside the project country (cases (c) and (d) above under Source of data), it is necessary to validate the applicability of BCEFs used. Validation is performed by:
	1. Limited Measurements
	• Select at least 20 plots in the project area covering a wide range of commercial volumes.
	• Obtain tree measurements (e.g. DBH, height to a 10 cm diameter top) from which to calculate commercial volume and total biomass.
	• Calculate commercial volume per unit area (e.g. using Smalian's formula) and total biomass per unit area (using the

- biomass equation(s) selected for application in CP-AB) for each plot.
- Calculate BCEF for each plot (biomass (t) / commercial volume (m3).

Graph the plot-level estimates of BCEF versus commercial volume along with the BCEF equation (predicted) to be validated. If the estimated BCEFs of the measured plots are distributed both above and below the predicted value the BCEF equation may be used. The BCEF equation may also be used if the measured plots have a BCEF consistently lower than that predicted. If graphing the BCEF of the measured plots indicates a systematic bias to overestimation of BCEF (>75% of the plots below the predicted value) then another BCEF equation must be selected or developed anew.

Data / Parameter	CF_j
Data unit	t C t^{-1} d.m.
Description	Carbon fraction of dry matter in t C t^{-1} d.m. for species j
Equations	4
Source of data	Species- or family-specific values from the literature (e.g. IPCC 2006 INV GLs AFOLU Chapter 4 Table 4.3) shall be used if available, otherwise default value of 0.47 t C t-1 d.m. can be used.
Value applied	-
Justification of choice of data or description of measurement methods and procedures applied	-
Purpose of Data	Calculation of baseline emissions
Comments	Where new species are encountered in the course of monitoring, new carbon fraction values must be sourced from the literature or otherwise use the default value.

Data / Parameter	D_j
Data unit	t d.m. m^{-3}
Description	Basic wood density in t d.m. m^{-3} for species j
Equations	4
Source of data	The source of data shall be chosen with priority from higher to lower preference as follows: a) National species-specific or group of species-specific (e.g. from National GHG inventory);

	b) Species-specific or group of species-specific from neighboring countries with similar conditions. Sometimes (b) may be preferable to (a);
	c) Global species-specific or group of species-specific (e.g. IPCC 2006 INV GLs AFOLU Chapter 4 Tables 4.13 and 4.14).
	Species-specific wood densities may not always be available, and may be difficult to apply with certainty in the typically species rich forests of the humid tropics, hence it is acceptable practice to use wood densities developed for forest types or plant families or species groups.
Value applied	-
Justification of choice of data or description of measurement methods and procedures applied	-
Purpose of Data	Calculation of baseline emissions
Comments	Where using wood densities developed outside of the project country (cases (b) and (c) above under Source of data), wood densities must be validated with either limited destructive sampling or direct measurement of wood hardness (e.g. with a Pilodyn wood tester) in the field and correlating with wood density. Samples or measurements must be from 20-30 trees. For validation of mean forest type or species group wood densities, representation of species in the sample must be proportional to their occurrence in terms of basal area or volume in the project area (not abundance or stem density). Samples must provide representation across the length of the tree.
	Wood samples are cut in discs and thickness and diameter measured to calculate green volume. Samples are oven dried (70o C) to a constant weight in the laboratory, and density calculated as dry weight (g) per unit green volume (cm³).
	If the density of the samples/measurements (or mean density in the case of forest type or species group means) is within ±10% of the selected density values, then the selected density values may be used. Otherwise, a new density value must be developed with more extensive sampling, using the validation samples as a base.
	Where new species are encountered in the course of monitoring, new wood density values must be sourced from the literature and validated, if necessary, as per requirements and procedures above.

Data / Parameter	$Pcom_i$
Data unit	Dimensionless
Description	Commercial volume as a percent of total aboveground volume in stratum i.
Equations	1

Source of data	The source of data shall be chosen with priority from higher to lower preference as follows: a) Direct forest inventory of the project area, distinguishing commercially viable stocks on the basis of species and tree size, referencing local expert knowledge or a participatory rural assessment (PRA) of harvest practices and markets; b) Forest inventory from a proxy area in the same region, representing the same forest type and age class, distinguishing commercially viable stocks on the basis of species and tree size, referencing local expert knowledge of harvest practices and markets National and forest type-specific or eco-region-specific (e.g. from National GHG inventory).
Value applied	-
Justification of choice of data or description of measurement methods and procedures applied	This parameter is updated at baseline renewal when aboveground biomass is re-inventoried as per module CP-AB (at least every 10 years).
Purpose of Data	Calculation of baseline emissions
Comments	Updated at the time of baseline revision (at least every 10 years). Note that application of the commercial percentage of total volume introduces the simplifying assumption (and conservative, as it is only used in the ex-ante baseline calculations) that all commercial stocks are extracted (i.e. perfect efficiency).

Data / Parameter	SLF_{ty}
Data unit	Dimensionless
Description	Fraction of wood products that will be emitted to the atmosphere within 5 years of production by class of wood product ty
Equations	2, 4
Source of data	The source of data is the published paper of Winjum *et al.* 1998[1] Winjum et al. 1998 give the following proportions for wood products with short-term (<5 yr) uses after which they are retired and oxidized (applicable internationally): Sawnwood 0.2 Woodbase panels 0.1 Other industrial roundwood 0.3 Paper and Paperboard 0.4 The methodology makes the assumption that all other classes of wood products, and where wood product class ty is unknown, are 100% oxidized within 5 years.

---

[1] Winjum, J.K., Brown, S. and Schlamadinger, B. 1998. Forest harvests and wood products: sources and sinks of atmospheric carbon dioxide. *Forest Science* 44: 272-284

Value applied	
	<table><tr><th>Wood Product Class</th><th>SLF</th></tr><tr><td>Sawnwood</td><td>0.2</td></tr><tr><td>Woodbase panels</td><td>0.1</td></tr><tr><td>Other industrial roundwood</td><td>0.3</td></tr><tr><td>Paper and paperboard</td><td>0.4</td></tr><tr><td>Other classes of wood products</td><td>1.0</td></tr></table>
Justification of choice of data or description of measurement methods and procedures applied	-
Purpose of Data	Calculation of baseline emissions
Comments	Parameter values to be updated if new empirically-based peer-reviewed findings become available.

Data / Parameter	WW_{ty}
Data unit	Dimensionless
Description	WW = Fraction of extracted biomass effectively emitted to the atmosphere during production by class of wood product *ty* Winjum *et al*. 1998 indicate that the proportion of extracted biomass that is oxidized (burning or decaying) from the production of commodities to be equal to 19% for developed countries, 24% for developing countries. WW is therefore equal to $C_{xb,ty}$ multiplied by 0.19 for developed countries and 0.24 for developing countries.
Equations	2, 4
Source of data	The source of data is the published paper of Winjum *et al*. 1998
Value applied	-
Justification of choice of data or description of measurement methods and procedures applied	-
Purpose of Data	Calculation of baseline emissions
Comments	Parameter values to be updated if new empirically-based peer-reviewed findings become available.

6.2   Data and Parameters Monitored

Data / Parameter:	A_i
Data unit:	ha
Description:	Total area of stratum i
Equations	3
Source of data:	The source of data shall be chosen with priority from higher to lower preference as follows: a) Direct forest inventory of the project area, distinguishing commercially viable stocks on the basis of species and tree size, referencing local expert knowledge or a participatory rural assessment (PRA) of harvest practices and markets; b) Forest inventory from a proxy area in the same region, representing the same forest type and age class, distinguishing commercially viable stocks on the basis of species and tree size, referencing local expert knowledge of harvest practices and markets National and forest type-specific or eco-region-specific (e.g. from National GHG inventory).
Description of measurement methods and procedures to be applied:	This parameter is updated at baseline renewal when aboveground biomass is re-inventoried as per module CP-AB (at least every 10 years).
Frequency of monitoring/recording:	At a minimum every time the baseline is updated (at least every 10 years).
QA/QC procedures to be applied:	-
Purpose of data:	Calculation of baseline emissions
Calculation method:	-
Comments:	*Ex-ante* it shall be assumed that strata area will remain constant.

Data / Parameter:	$V_{ex,j}$
Data unit:	m³
Description:	The volume of timber in m³ extracted from within the stratum (does not include slash left onsite), reported by wood product class and preferably species.
Equations	3
Source of data:	Timber harvest records and/or estimates derived from field measurements or remote assessments with aerial photography or satellite imagery.
Description of measurement methods and procedures to be applied:	-
Frequency of monitoring/recording:	At a minimum every time the baseline is updated (at least every 10 years).

QA/QC procedures to be applied:	-
Purpose of data:	Calculation of baseline emissions
Calculation method:	-
Comments:	Note that this volume does not include logging slash left onsite. Data compilers must also make sure that extracted volumes reported are gross volumes removed (i.e. reported volume does not already discount for estimated wood waste, as is often the practice in harvest records). Assignment of volume extracted to wood product class(es), be substantiated on the basis of participatory rural appraisal (PRA) findings (also used to assess potential for degradation in module M-MON) or records of timber sales. Assignment of volume extracted to species, must be substantiated on the basis of either PRA findings, harvest records, or a commercial inventory. Baseline removals will be known ex-ante. With project removals are classed as project emissions and where expected shall be detailed ex-ante alongside evidence on expected harvested volumes.

DOCUMENT HISTORY

Version	Date	Comment
v1.0	3 Dec 2010	Initial version released
v1.1	20 Nov 2012	The module was updated to appropriately account for the decay of carbon harvested wood products pool and the following revisions were made: • Equations 2 and 5 are revised so that only the wood waste fraction is immediately released. • Equations 3 and 6 are revised to calculate the total amount of wood that is expected to be emitted over a 100-year timeframe which include both the short-term and medium-term portions.
v1.2	27 Nov 2023	• Update to latest VCS methodology template • Removal of references to VM0007